

# iPad Clutch Skill Level: Beginner

Designed By
Darlene Christopherson
and
Alexandra Henry
Sewn By
Judy Steward



As seen in the Premier Issue of <u>Quilts 1.2.3</u> Magazine. Protect your iPad from scratches with this quick and easy clutch. Pellon® stabilizers make it fast, fun, and easy.



#### **Fabric Needed**

Exterior Fabric - Keepsake Calico Fanciful Swirl turquoise #1885185 Lining - Fall Blessings, Harvest Circles #10005486 Binding - Keepsake Calico Lt Green, Small Floral #7966237 Cut one 11" x 22%"
Cut one 11" x 22%"
One fat quarter (expect leftovers)

### **Materials Needed**

Pellon® 809 Décor-Bond® Stabilizer Pellon® 987F Fusible Fleece Pellon® 805 Wonder-Under® Thread

Cut one 11" x 22%" rectangle Cut one 11" x 22%" rectangle 1/4 yd

### **Tools Needed**

Rotary Cutting tools and mat Ruler Sewing machine and related supplies

## **Assembly**

Step 1. Fuse the Décor-Bond® to the wrong side of the 11" x 22%" rectangle lining piece.

Step 2. Fuse the Fusible Fleece to the wrong side of the  $11'' \times 22\%$  exterior piece.

Step 3. Cut one 11" x 22%" rectangle from the Wonder-Under®.

Step 4. Print and cut out the triangle template. Lay the template on the wrong side of one end of each fabric rectangle aligning the side of the template on the side of the rectangle. Draw one half of the triangle end on the wrong side of both the lining and exterior fabrics. Flip the template and draw the other side. Cut on the two sides for the triangle, do not cut on the fold line. Repeat this step for the rectangle of Wonder-Under®.


Step 5. Mark the flap center and the flap fold line (see template).


Step 6. Fuse the piece of Wonder-Under® to the wrong side of the exterior fabric. Remove the paper from Wonder-Under®. Place the exterior and lining fabrics wrong sides together. Fuse the layers together. Baste the layers using a large ¼" seam allowance around entire clutch.


Step 7. Fuse wrong side of the entire binding fat quarter to the fusible side of Wonder Under<sup>®</sup>.


Step 8. Place the binding fat quarter right side up on the rotary cutting mat. Place the ruler at a 45° angle from the top left corner to the bottom of the fabric. Cut along that line. Move the ruler and measure 1" from that cut line and cut a strip. Move the ruler 1" and cut a second piece. Cut two 1" strips from the other half.

OPTIONAL: Use a wavy rotary blade to cut these strips.









Step 9. Remove the Wonder-Under® paper from the binding strips.

Step 10. Set the shortest binding strip aside. Sew the remaining binding strips together by placing the ends of them at a  $90^{\circ}$  angle and stitch on a diagonal as shown. Trim seam allowance to  $\frac{1}{4}$ ". Press seams to create a strip of binding 35" long.


Step 11. Fold the strips wrong sides together lengthwise.


Step 12. Finger press both binding strips carefully the entire length.

Step 13. Take the shortest of the binding strips and place it over the straight edge of the clutch aligning the crease with the raw edge. Binding strip will cover both sides.


Step 14. Fuse into place.


Step 15. Trim edges even with clutch edges.






HINT: Gently pressing the Fusible Fleece and Décor-Bond® at the fold will increase its flexibility.









Step 18. Fold one end of the long 35" binding strip in  $\frac{1}{4}$ ". Fuse a small piece of Wonder-Under® onto the inside edge of the  $\frac{1}{4}$ " fold as shown.





Step 19. Starting at the bottom left edge, place binding with the turned in edge over the clutch, aligning the crease of the binding strip with the raw edge of the clutch. Fuse binding in place stopping close to first angle. Bend binding around the angle, creating a diagonal fold (miter) and align the next few inches over the raw edge. Fuse into place. Continue fusing binding repeating the diagonal miter at the next two angles. Continue fusing binding around the clutch until ½" from end of the last side. Cut binding ¼" past the end, turn in and fuse into place.

Step 20. Sew the edge of the binding \%" from inside edge with a straight or decorative stitch. Decorate flap with a button.

Step 21. Attach a decorative frog closure or velcro closure if desired.

HINT: Gently press the flap to increase flexibility and fold down.







Detail of iPad Flap

